

KEYBOARD LAYOUT SUPERIOR DRUMMER 3

KEYBOARD LAYOUT

65	[Hi-Hat]	Seq Hits	
64		Open Min	
63		Tight Tip	
62		Tight Edge	
61		Closed Tip	
60		Open Max	C3
59	[Ride]	Crashed	
58	[Cymbal 4]	Muted	
57		Crashed	
56	[Cymbal 3]	Muted	
55		Crashed	
54	[Cymbal 5]	Muted	
53	[Ride]	Bell Shank	
52	[Cymbal 5]	Crashed	
51	[Ride]	Bow Tip	
50	[Cymbal 2]	Muted	
49		Crashed	
48	[Racktom 1]	Center	C2
47	[Racktom 2]	Center	
46	[Hi-Hat] {GM}	Open	
45	[Racktom 3]	Center	
44	[Hi-Hat] {GM}	Pedal	
43	[Floortom 1]	Center	
42	[Hi-Hat] {GM}	Closed	
41	[Floortom 2]	Center	
40	[Snare]	Rimshot	
39		Ruffs	
38		Center	
37		Sidestick	
36	[Kick]	Open	C1
35		Hit	
34		alias	
33	[Snare]	Edge	
32	[Cymbal 5]	alias	
31	[Cymbal 4]	alias	
30	[Ride]	alias	
29	[Cymbal 3]	alias	
28	[Cymbal 2]	alias	
27	[Cymbal 1]	Crashed	
26	[Hi-Hat]	Open 3	
25		Open 2	C0
24		Open 1	
23		Open Pedal	
22		Closed Edge	
21		Closed Pedal	
20	[Hi-Hat] {CC}	Shaft Trig	
19		Tip Trig	
18		Edge Trig	
17	[Hi-Hat]	Open Tip 5	
16		Open Tip 4	
15		Open Tip 3	
14		Open Tip 2	
13		Open Tip 1	
12		Open Tip 0	-C1
11		alias	
10		alias	
9	[Hi-Hat] {CC}	Bell Trig	
8		alias	
7		alias	
6	[Snare] {CC}	Position Trig	

127	[Brushes]	Forward	
126		Backward	
125	[Snare]	Mid Center	
124	[Hi-Hat]	Open Bell 4	
123		Open Bell 3	
122		Open Bell 2	
121		Open Bell 1	
120		Open Bell 0	C8
119		Closed Bell	
118	[Ride]	Muted	
117		Bell Tip	
116		Bow Shank	
115		alias	
114		alias	
113		alias	
112	[Cymbal 5]	Bell Tip	
111		Bow Shank	
110		alias	
109		Bell Shank	
108		Bow Tip	C7
107		alias	
106	[Cymbal 4]	alias	
105		Bell Tip	
104		Bow Shank	
103		alias	
102		Bell Shank	
101		Bow Tip	
100	[Cymbal 3]	Bell Tip	
99		Bow Shank	
98		alias	
97		Bell Shank	
96		Bow Tip	C6
95		alias	
94	[Cymbal 2]	alias	
93		Bell Tip	
92		Bow Shank	
91		alias	
90		Bell Shank	
89		Bow Tip	
88	[Cymbal 1]	Bell Tip	
87		Bow Shank	
86		alias	
85		Bell Shank	
84		Bow Tip	C5
83		Muted	
82	[Racktom 1]	Rimshot	
81		Rim Only	
80	[Racktom 2]	Rimshot	
79		Rim Only	
78	[Racktom 3]	Rimshot	
77		Rim Only	
76	[Snare]	alias	
75	[Floortom 1]	Rimshot	
74		Rim Only	
73	[Floortom 2]	Rimshot	
72		Rim Only	C4
71	[Snare]	Rim Only	
70		Thump	
69		Flam	
68	[Brushes]	Muted Hit	
67		Fwd Swirl	
66		Back Swirl	

1-5 are reserved for sampler features

This product uses



SDX™

EXPANSION PACK FOR SUPERIOR DRUMMER 3®

TOONTRACK